B1. Object Files (.obj)

Object files define the geometry and other properties for objects in Wavefront's Advanced Visualizer. Object files can also be used to transfer geometric data back and forth between the Advanced Visualizer and other applications.

Object files can be in ASCII format (.obj) or binary format (.mod). This appendix describes the ASCII format for object files. These files must have the extension *.obj*.

In this release, the .obj file format supports both *polygonal* objects and *free-form* objects. Polygonal geometry uses points, lines, and faces to define objects while free-form geometry uses curves and surfaces.

About this section

The .obj appendix is for those who want to use the .obj format to translate geometric data from other software applications to Wavefront products. It also provides information for Advanced Visualizer users who want detailed information on the Wavefront .obj file format.

If you are a 2.11 user and want to understand the significance of the 3.0 release and how it affects your existing files, you may be especially interested in the section called "Superseded statements" at the end of the appendix. The section, "Patches and free-form surfaces," gives examples of how 2.11 patches look in 3.0.

How this section is organized

Most of this appendix describes the different parts of an .obj file and how those parts are arranged in the file. The three sections at the end of the appendix provide background information on the 3.0 release of the .obj format.

The .obj appendix includes the following sections:

- File structure
- General statement
- Vertex data
- Specifying free-form curves/surfaces
- Free-form curve/surface attributes
- Elements
- Free-form curve/surface body statements
- Connectivity between free-form surfaces
- Grouping
- Display/render attributes
- Comments
- Mathematics for free-form curves/surfaces
- Superseded statements
- Patches and free-form surfaces

The curve and surface extensions to the .obj file format were developed in conjunction with mental images GmbH&Co.KG, Berlin, Germany, as part of a joint development project to incorporate free-form surfaces into Wavefront's Advanced Visualizer.

File structure

The following types of data may be included in an .obj file. In this list, the keyword (in parentheses) follows the data type.

Vertex data

- geometric vertices (*v*)
- texture vertices (*vt*)
- vertex normals (*vn*)
- parameter space vertices (*vp*)

Free-form curve/surface attributes

- rational or non-rational forms of curve or surface type: basis matrix, Bezier, B-spline, Cardinal, Taylor (*cstype*)
- degree (*deg*)
- basis matrix (*bmat*)
- step size (*step*)

Elements

- point (*p*)
- line (*l*)
- face (*f*)
- curve (*curv*)
- 2D curve (*curv2*)
- surface (*surf*)

Free-form curve/surface body statements

- parameter values (*parm*)
- outer trimming loop (*trim*)
- inner trimming loop (*hole*)
- special curve (*scrv*)
- special point (*sp*)
- end statement (*end*)

Connectivity between free-form surfaces

- connect (*con*)

Grouping

- group name (*g*)
- smoothing group (*s*)
- merging group (*mg*)
- object name (*o*)

Display/render attributes

- bevel interpolation (*bevel*)
- color interpolation (*c_interp*)
- dissolve interpolation (*d_interp*)
- level of detail (*lod*)
- material name (*usemtl*)
- material library (*mtllib*)
- shadow casting (*shadow_obj*)
- ray tracing (*trace_obj*)
- curve approximation technique (*ctech*)
- surface approximation technique (*stech*)

The following diagram shows how these parts fit together in a typical .obj file.



Figure B1-1. Typical .obj file structure

General statement

call *filename.ext* *arg1 arg2 . . .*

Reads the contents of the specified .obj or .mod file at this location. The call statement can be inserted into .obj files using a text editor.

filename.ext is the name of the .obj or .mod file to be read. You must include the extension with the filename.

arg1 arg2 . . . specifies a series of optional integer arguments that are passed to the called file. There is no limit to the number of nested calls that can be made.

Arguments passed to the called file are substituted in the same way as in UNIX scripts; for example, *$1* in the called file is replaced by *arg1*, *$2* in the called file is replaced by *arg2*, and so on.

If the frame number is needed in the called file for variable substitution, "$1" must be used as the first argument in the call statement. For example:

```
call filename.obj $1
```

Then the statement in the called file,

```
scmp filename.pv $1
```

will work as expected. For more information on the scmp statement, see appendix C, Variable Substitution for more information.

Another method to do the same thing is:

```
scmp filename.pv $1
call filename.obj
```

Using this method, the *scmp* statement provides the .pv file for all subsequently called .obj or .mod files.

csh *command*
csh -*command*

Executes the requested UNIX command. If the UNIX command returns an error, the parser flags an error during parsing.

If a dash (-) precedes the UNIX command, the error is ignored.

command is the UNIX command.

Vertex data

Vertex data provides coordinates for:

- geometric vertices
- texture vertices
- vertex normals

For free-form objects, the vertex data also provides:

- parameter space vertices

The vertex data is represented by four vertex lists; one for each type of vertex coordinate. A right-hand coordinate system is used to specify the coordinate locations.

The following sample is a portion of an .obj file that contains the four types of vertex information.

```
v    -5.000000  5.000000  0.000000
v    -5.000000 -5.000000  0.000000
v     5.000000 -5.000000  0.000000
v     5.000000  5.000000  0.000000
vt   -5.000000  5.000000  0.000000
vt   -5.000000 -5.000000  0.000000
vt    5.000000 -5.000000  0.000000
vt    5.000000  5.000000  0.000000
vn    0.000000  0.000000  1.000000
vn    0.000000  0.000000  1.000000
vn    0.000000  0.000000  1.000000
vn    0.000000  0.000000  1.000000
vp    0.210000  3.590000
vp    0.000000  0.000000
vp    1.000000  0.000000
vp    0.500000  0.500000
```

When vertices are loaded into the Advanced Visualizer, they are sequentially numbered, starting with 1. These reference numbers are used in element statements.

Syntax

The following syntax statements are listed in order of complexity.

v *x y z* w

Polygonal and free-form geometry statement.
Specifies a geometric vertex and its x y z coordinates. Rational curves and surfaces require a fourth homogeneous coordinate, also called the *weight*.

x y z are the x, y, and z coordinates for the vertex. These are floating point numbers that define the position of the vertex in three dimensions.

w is the weight required for rational curves and surfaces. It is not required for non-rational curves and surfaces. If you do not specify a value for *w*, the default is 1.0.

NOTE: A positive weight value is recommended. Using zero or negative values may result in an undefined point in a curve or surface.

---

vp *u* *v w*

Free-form geometry statement.
Specifies a point in the parameter space of a curve or surface.

The usage determines how many coordinates are required. Special points for curves require a 1D control point (u only) in the parameter space of the curve. Special points for surfaces require a 2D point (u and v) in the parameter space of the surface. Control points for non-rational trimming curves require u and v coordinates. Control points for rational trimming curves require u, v, and w (weight) coordinates.

u is the point in the parameter space of a curve or the first coordinate in the parameter space of a surface.

v is the second coordinate in the parameter space of a surface.

w is the weight required for rational trimming curves. If you do not specify a value for *w*, it defaults to 1.0.

NOTE: For additional information on parameter vertices, see the *curv2* and *sp* statements

---

vn *i j k*

Polygonal and free-form geometry statement.
Specifies a normal vector with components i, j, and k.

Vertex normals affect the smooth-shading and rendering of geometry. For polygons, vertex normals are used in place of the actual facet normals. For surfaces, vertex normals are interpolated over the entire surface and replace the actual analytic surface normal.

When vertex normals are present, they supersede smoothing groups.

i j k are the i, j, and k coordinates for the vertex normal. They are floating point numbers.

vt *u* *v w*

Vertex statement for both polygonal and free-form geometry. Specifies a texture vertex and its coordinates. A 1D texture requires only *u* texture coordinates, a 2D texture requires both *u* and *v* texture coordinates, and a 3D texture requires all three coordinates.

u is the value for the horizontal direction of the texture.

v is an optional argument.
v is the value for the vertical direction of the texture. The default is 0.

w is an optional argument.
w is a value for the depth of the texture. The default is 0.

Specifying free-form curves/surfaces

There are three steps involved in specifying a free-form curve or surface element.

- Specify the type of curve or surface (basis matrix, Bezier, B-spline, Cardinal, or Taylor) using free-form curve/surface attributes.
- Describe the curve or surface with element statements.
- Supply additional information, using free-form curve/surface body statements

The next three sections of this appendix provide detailed information on each of these steps.

Data requirements for curves and surfaces

All curves and surfaces require a certain set of data. This consists of the following:

Free-form curve/surface attributes

- All curves and surfaces require type data, which is given with the *cstype* statement.
- All curves and surfaces require degree data, which is given with the *deg* statement.
- Basis matrix curves or surfaces require a *bmat* statement.
- Basis matrix curves or surfaces also require a step size, which is given with the *step* statement.

Elements

- All curves and surfaces require control points, which are referenced in the c*urv*, c*urv2*, or s*urf* statements.
- 3D curves and surfaces require a parameter range, which is given in the c*urv* and s*urf* statements, respectively.

Free-form curve/surface body statements

- All curves and surfaces require a set of global parameters or a knot vector, both of which are given with the *parm* statement.
- All curves and surfaces body statements require an explicit *end* statement.

Error checks

The above set of data starts out empty with no default values when reading of an .obj file begins. While the file is being read, statements are encountered, information is accumulated, and some errors may be reported.

When the end statement is encountered, the following error checks, which involve consistency between various statements, are performed:

- All required information is present.
- The number of control points, number of parameter values (knots), and degree are consistent with the curve or surface type. If the type is *bmatrix*, the step size is also consistent. (For more information, refer to the parameter vector equations in the section, "Mathematics of free-form curves/ surfaces" at the end of appendix B1.)
- If the type is *bmatrix* and the degree is n, the size of the basis matrix is $(n + 1) \times (n + 1)$.

Note that any information given by the state-setting statements remains in effect from one curve or surface to the next. Information given within a curve or surface body is only effective for the curve or surface it is given with.

Free-form curve/surface attributes

Five types of free-form geometry are available in the .obj file format:

- Bezier
- basis matrix
- B-spline
- Cardinal
- Taylor

You can apply these types only to curves and surfaces. Each of these five types can be rational or non-rational.

In addition to specifying the type, you must define the degree for the curve or surface. For basis matrix curve and surface elements, you must also specify the basis matrix and step size.

All free-form curve and surface attribute statements are state-setting. This means that once an attribute statement is set, it applies to all elements that follow until it is reset to a different value.

Syntax

The following syntax statements are listed in order of use.

cstype rat ***type***

Free-form geometry statement.
Specifies the type of curve or surface and indicates a rational or non-rational form.

rat is an optional argument.
rat specifies a rational form for the curve or surface type. If *rat* is not included, the curve or surface is non-rational

type specifies the curve or surface type. Allowed types are:

bmatrix	basis matrix
bezier	Bezier
bspline	B-spline
cardinal	Cardinal
taylor	Taylor

There is no default. A value must be supplied.

deg *degu* *degv*

Free-form geometry statement.
Sets the polynomial degree for curves and surfaces.

degu is the degree in the u direction. It is required for both curves and surfaces.

degv is the degree in the v direction. It is required only for surfaces. For Bezier, B-spline, Taylor, and basis matrix, there is no default; a value must be supplied. For Cardinal, the degree is always 3. If some other value is given for Cardinal, it will be ignored.

bmat *u matrix*
bmat *v matrix*

Free-form geometry statement.
Sets the basis matrices used for basis matrix curves and surfaces. The u and v values must be specified in separate *bmat* statements.

NOTE: The *deg* statement must be given before the *bmat* statements and the size of the matrix must be appropriate for the degree.

---

u specifies that the basis matrix is applied in the u direction.

v specifies that the basis matrix is applied in the v direction.

matrix lists the contents of the basis matrix with column subscript *j* varying the fastest. If *n* is the degree in the given u or v direction, the matrix (*i,j*) should be of size *(n + 1)* x *(n + 1*).

There is no default. A value must be supplied.

NOTE: The arrangement of the matrix is different from that commonly found in other references. For more information, see the examples at the end of this section and also the section, "Mathematics for free-form curves and surfaces."

---

step *stepu* *stepv*

Free-form geometry statement.
Sets the step size for curves and surfaces that use a basis matrix.

stepu is the step size in the *u* direction. It is required for both curves and surfaces that use a basis matrix.

stepv is the step size in the *v* direction. It is required only for surfaces that use a basis matrix. There is no default. A value must be supplied.

When a curve or surface is being evaluated and a transition from one segment or patch to the next occurs, the set of control points used is incremented by the step size. The appropriate step size depends on the representation type, which is expressed through the basis matrix, and on the degree.

That is, suppose we are given a curve with k control points:

$$\{\mathbf{v}_1, \ldots, \mathbf{v}_k\}$$

If the curve is of degree n, then $n + 1$ control points are needed for each polynomial segment. If the step size is given as s, then the ith polynomial segment, where $i = 0$ is the first segment, will use the control points:

$$\{\mathbf{v}_{is+1}, \ldots, \mathbf{v}_{is+n+1}\}$$

For example, for Bezier curves, $s = n$.

For surfaces, the above description applies independently to each parametric direction.

When you create a file which uses the basis matrix type, be sure to specify a step size appropriate for the current curve or surface representation.

Examples

1. Cubic Bezier surface made with a basis matrix

To create a cubic Bezier surface:

```
cstype bmatrix
deg 3 3
step 3 3
bmat u  1 -3  3 -1 \
        0  3 -6  3 \
        0  0  3 -3 \
        0  0  0  1
bmat v  1 -3  3 -1 \
        0  3 -6  3 \
        0  0  3 -3 \
        0  0  0  1
```

2. Hermite curve made with a basis matrix

To create a Hermite curve:

```
cstype bmatrix
deg 3
step 2
bmat u  1  0 -3  2  0  0  3 -2  \
        0  1 -2  1  0  0 -1  1
```

3. Bezier in u direction with B-spline in v direction; made with a basis matrix

To create a surface with a cubic Bezier in the u direction and cubic uniform B-spline in the v direction:

```
cstype bmatrix
deg 3 3
step 3 1
bmat u  1 -3  3 -1 \
        0  3 -6  3 \
        0  0  3 -3 \
        0  0  0  1
bmat v  0.16666 -0.50000  0.50000 -0.16666 \
        0.66666  0.00000 -1.00000  0.50000 \
        0.16666  0.50000  0.50000 -0.50000 \
        0.00000  0.00000  0.00000  0.16666
```

Elements

For polygonal geometry, the element types available in the .obj file are:

- points
- lines
- faces

For free-form geometry, the element types available in the .obj file are:

- curve
- 2D curve on a surface
- surface

All elements can be freely intermixed in the file.

Referencing vertex data

For all elements, reference numbers are used to identify geometric vertices, texture vertices, vertex normals, and parameter space vertices.

Each of these types of vertices is numbered separately, starting with 1. This means that the first geometric vertex in the file is 1, the second is 2, and so on. The first texture vertex in the file is 1, the second is 2, and so on. The numbering continues sequentially throughout the entire file. Frequently, files have multiple lists of vertex data. This numbering sequence continues even when vertex data is separated by other data.

In addition to counting vertices down from the top of the first list in the file, you can also count vertices back up the list from an element's position in the file. When you count up the list from an element, the reference numbers are negative. A reference number of -1 indicates the vertex immediately above the element. A reference number of -2 indicates two references above and so on.

Referencing groups of vertices

Some elements, such as faces and surfaces, may have a triplet of numbers that reference vertex data.These numbers are the reference numbers for a geometric vertex, a texture vertex, and a vertex normal.

Each triplet of numbers specifies a geometric vertex, texture vertex, and vertex normal. The reference numbers must be in order and must separated by slashes (/).

- The first reference number is the geometric vertex.
- The second reference number is the texture vertex. It follows the first slash.
- The third reference number is the vertex normal. It follows the second slash.

There is no space between numbers and the slashes. There may be more than one series of geometric vertex/texture vertex/vertex normal numbers on a line.

The following is a portion of a sample file for a four-sided face element:

```
f 1/1/1 2/2/2 3/3/3 4/4/4
```

Using v, vt, and vn to represent geometric vertices, texture vertices, and vertex normals, the statement would read:

```
f v/vt/vn v/vt/vn v/vt/vn v/vt/vn
```

If there are only vertices and vertex normals for a face element (no texture vertices), you would enter two slashes (//). For example, to specify only the vertex and vertex normal reference numbers, you would enter:

```
f 1//1 2//2 3//3 4//4
```

When you are using a series of triplets, you must be consistent in the way you reference the vertex data. For example, it is illegal to give vertex normals for some vertices, but not all.

The following is an example of an **illegal statement**.

```
f 1/1/1 2/2/2 3//3 4//4
```

Syntax

The following syntax statements are listed in order of complexity of geometry.

p ***v1*** *v2 v3 . . .*

Polygonal geometry statement.
Specifies a point element and its vertex. You can specify multiple points with this statement. Although points cannot be shaded or rendered, they are used by other Advanced Visualizer programs.

v is the vertex reference number for a point element. Each point element requires one vertex. Positive values indicate absolute vertex numbers. Negative values indicate relative vertex numbers.

l ***v1****/vt1* ***v2****/vt2* ***v3****/vt3 . . .*

Polygonal geometry statement.
Specifies a line and its vertex reference numbers. You can optionally include the texture vertex reference numbers. Although lines cannot be shaded or rendered, they are used by other Advanced Visualizer programs.

The reference numbers for the vertices and texture vertices must be separated by a slash (/). There is no space between the number and the slash.

v is a reference number for a vertex on the line. A minimum of two vertex numbers are required. There is no limit on the maximum. Positive values indicate absolute vertex numbers. Negative values indicate relative vertex numbers.

vt is an optional argument.
vt is the reference number for a texture vertex in the line element. It must always follow the first slash.

f ***v1****/vt1/vn1* ***v2****/vt2/vn2* ***v3****/vt3/vn3 . . .*

Polygonal geometry statement.
Specifies a face element and its vertex reference number. You can optionally include the texture vertex and vertex normal reference numbers.

The reference numbers for the vertices, texture vertices, and vertex normals must be separated by slashes (/). There is no space between the number and the slash.

v is the reference number for a vertex in the face element. A minimum of three vertices are required.

vt is an optional argument.
vt is the reference number for a texture vertex in the face element. It always follows the first slash.

vn is an optional argument.
vn is the reference number for a vertex normal in the face element. It must always follow the second slash.

Face elements use surface normals to indicate their orientation. If vertices are ordered counterclockwise around the face, both the face and the normal will point toward the viewer. If the vertex ordering is clockwise, both will point away from the viewer. If vertex normals are assigned, they should point in the general direction of the surface normal, otherwise unpredictable results may occur.

If a face has a texture map assigned to it and no texture vertices are assigned in the *f* statement, the texture map is ignored when the element is rendered.

NOTE: Any references to *fo* (face outline) are no longer valid as of version 2.11. You can use *f* (face) to get the same results. References to *fo* in existing .obj files will still be read, however, they will be written out as *f* when the file is saved.

---

curv *u0 u1 v1 v2* . . .

Element statement for free-form geometry.
Specifies a curve, its parameter range, and its control vertices. Although curves cannot be shaded or rendered, they are used by other Advanced Visualizer programs.

u0 is the starting parameter value for the curve. This is a floating point number.

u1 is the ending parameter value for the curve. This is a floating point number.

v is the vertex reference number for a control point. You can specify multiple control points. A minimum of two control points are required for a curve.

For a non-rational curve, the control points must be 3D. For a rational curve, the control points are 3D or 4D. The fourth coordinate (weight) defaults to 1.0 if omitted.

curv2 ***vp1 vp2*** *vp3. . .*

Free-form geometry statement.
Specifies a 2D curve on a surface and its control points. A 2D curve is used as an outer or inner trimming curve, as a special curve, or for connectivity.

vp is the parameter vertex reference number for the control point. You can specify multiple control points. A minimum of two control points is required for a 2D curve.

The control points are parameter vertices because the curve must lie in the parameter space of some surface. For a non-rational curve, the control vertices can be 2D. For a rational curve, the control vertices can be 2D or 3D. The third coordinate (weight) defaults to 1.0 if omitted.

surf ***s0 s1 t0 t1 v1****/vt1/vn1 v2/vt2/vn2 . . .*

Element statement for free-form geometry.
Specifies a surface, its parameter range, and its control vertices. The surface is evaluated within the global parameter range from *s0* to *s1* in the *u* direction and *t0* to *t1* in the *v* direction.

s0 is the starting parameter value for the surface in the u direction.

s1 is the ending parameter value for the surface in the u direction.

t0 is the starting parameter value for the surface in the v direction.

t1 is the ending parameter value for the surface in the v direction.

v is the reference number for a control vertex in the surface.

*v*t is an optional argument.
vt is the reference number for a texture vertex in the surface. It must always follow the first slash.

vn is an optional argument.
vn is the reference number for a vertex normal in the surface. It must always follow the second slash.

For a non-rational surface the control vertices are 3D. For a rational surface the control vertices can be 3D or 4D. The fourth coordinate (weight) defaults to 1.0 if omitted.

NOTE: For more information on the ordering of control points for surfaces, refer to the section on surfaces and control points in "Mathematics of free-form curves/surfaces" at the end of this appendix.

Examples

These are examples for polygonal geometry.

For examples using free-form geometry, see the examples at the end of the next section, “Free-form curve/surface body statements.”

1. Square

This example shows a square that measures two units on each side and faces in the positive direction (toward the camera). Note that the ordering of the vertices is counterclockwise. This ordering determines that the square is facing forward.

```
v 0.000000 2.000000 0.000000
v 0.000000 0.000000 0.000000
v 2.000000 0.000000 0.000000
v 2.000000 2.000000 0.000000
f 1 2 3 4
```

2. Cube

This is a cube that measures two units on each side. Each vertex is shared by three different faces.

```
v 0.000000 2.000000 2.000000
v 0.000000 0.000000 2.000000
v 2.000000 0.000000 2.000000
v 2.000000 2.000000 2.000000
v 0.000000 2.000000 0.000000
v 0.000000 0.000000 0.000000
v 2.000000 0.000000 0.000000
v 2.000000 2.000000 0.000000
f 1 2 3 4
f 8 7 6 5
f 4 3 7 8
f 5 1 4 8
f 5 6 2 1
f 2 6 7 3
```

3. Cube with negative reference numbers

This is a cube with negative vertex reference numbers. Each element references the vertices stored immediately above it in the file. Note that vertices are not shared.

```
v 0.000000 2.000000 2.000000
v 0.000000 0.000000 2.000000
v 2.000000 0.000000 2.000000
v 2.000000 2.000000 2.000000
f -4 -3 -2 -1

v 2.000000 2.000000 0.000000
v 2.000000 0.000000 0.000000
v 0.000000 0.000000 0.000000
v 0.000000 2.000000 0.000000
f -4 -3 -2 -1

v 2.000000 2.000000 2.000000
v 2.000000 0.000000 2.000000
v 2.000000 0.000000 0.000000
v 2.000000 2.000000 0.000000
f -4 -3 -2 -1

v 0.000000 2.000000 0.000000
v 0.000000 2.000000 2.000000
v 2.000000 2.000000 2.000000
v 2.000000 2.000000 0.000000
f -4 -3 -2 -1

v 0.000000 2.000000 0.000000
v 0.000000 0.000000 0.000000
v 0.000000 0.000000 2.000000
v 0.000000 2.000000 2.000000
f -4 -3 -2 -1

v 0.000000 0.000000 2.000000
v 0.000000 0.000000 0.000000
v 2.000000 0.000000 0.000000
v 2.000000 0.000000 2.000000
f -4 -3 -2 -1
```

Free-form curve/surface body statements

You can specify additional information for free-form curve and surface elements using a series of statements called body statements. The series is concluded by an *end* statement.

Body statements are valid only when they appear between the free-form element statement (*curv*, *curv2*, *surf*) and the *end* statement. If they are anywhere else in the .obj file, they do not have any effect.

You can use body statements to specify the following values:

- parameter
- knot vector
- trimming loop
- hole
- special curve
- special point

You cannot use any other statements between the free-form curve or surface statement and the *end* statement. Using any other of type of statement may cause unpredictable results.

This portion of a sample file shows the knot vector values for a rational B-spline surface with a trimming loop. Notice the *end* statement to conclude the body statements.

```
cstype rat bspline
deg 2 2
surf -1.0 2.5 -2.0 2.0 -9 -8 -7 -6 -5 -4 -3 -2 -1
parm u -1.00 -1.00 -1.00 2.50 2.50 2.50
parm v -2.00 -2.00 -2.00 -2.00 -2.00 -2.00
trim 0.0 2.0 1
end
```

Parameter values and knot vectors

All curve and surface elements require a set of parameter values.

For polynomial curves and surfaces, this specifies global parameter values. For B-spline curves and surfaces, this specifies the knot vectors.

For surfaces, the parameter values must be specified for both the u and v directions. For curves, the parameter values must be specified for only the u direction.

If multiple parameter value statements for the same parametric direction are used inside a single curve or surface body, the last statement is used.

Trimming loops and holes

The trimming loop statement builds a single outer trimming loop as a sequence of curves which lie on a given surface.

The hole statement builds a single inner trimming loop as a sequence of curves which lie on a given surface. The inner loop creates a hole.

The curves are referenced by number in the same way vertices are referenced by face elements.

The individual curves must lie end-to-end to form a closed loop which does not intersect itself and which lies within the parameter range specified for the surface. The loop as a whole may be oriented in either direction (clockwise or counterclockwise).

To cut one or more holes in a region, use a trim statement followed by one or more hole statements. To introduce another trimmed region in the same surface, use another trim statement followed by one or more hole statements. The ordering that associates holes and the regions they cut is important and must be maintained.

If the first trim statement in the sequence is omitted, the enclosing outer trimming loop is taken to be the parameter range of the surface. If no trim or hole statements are specified, then the surface is trimmed at its parameter range.

This portion of a sample file shows a non-rational Bezier surface with two regions, each with a single hole:

```
cstype bezier
deg 1 1
surf 0.0 2.0 0.0 2.0 1 2 3 4
parm u 0.00 2.00
parm v 0.00 2.00
trim 0.0 4.0 1
hole 0.0 4.0 2
trim 0.0 4.0 3
hole 0.0 4.0 4
end
```

Special curve

A special curve statement builds a single special curve as a sequence of curves which lie on a given surface.

The curves are referenced by number in the same way vertices are referenced by face elements.

A special curve is guaranteed to be included in any triangulation of the surface. This means that the line formed by approximating the special curve with a sequence of straight line segments will actually appear as a sequence of triangle edges in the final triangulation.

Special point

A special point statement specifies that special geometric points are to be associated with a curve or surface. For space curves and trimming curves, the parameter vertices must be 1D. For surfaces, the parameter vertices must be 2D.

These special points will be included in any linear approximation of the curve or surface.

For space curves, this means that the point corresponding to the given curve parameter is included as one of the vertices in an approximation consisting of a sequence of line segments.

For surfaces, this means that the point corresponding to the given surface parameters is included as a triangle vertex in the triangulation.

For trimming curves, the treatment is slightly different: a special point on a trimming curve is essentially the same as a special point on the surface it trims.

The following portion of a sample files shows special points for a rational Bezier 2D curve on a surface.

```
vp -0.675  1.850  3.000
vp  0.915  1.930
vp  2.485  0.470  2.000
vp  2.485 -1.030
vp  1.605 -1.890 10.700
vp -0.745 -0.654  0.500
cstype rat bezier
curv2 -6 -5 -4 -3 -2 -1 -6
parm u 0.00 1.00 2.00
sp 2 3
end
```

Syntax

The following syntax statement are listed in order of normal use.

parm *u p1 p2* *p3. . .*
parm *v p1 p2* *p3 . . .*

Body statement for free-form geometry.
Specifies global parameter values. For B-spline curves and surfaces, this specifies the knot vectors.

u is the u direction for the parameter values.

v is the v direction for the parameter values.

To set *u* and *v* values, use separate command lines.

p is the global parameter or knot value. You can specify multiple values. A minimum of two parameter values are required. Parameter values must increase monotonically. The type of surface and the degree dictate the number of values required.

trim *u0 u1 curv2d* *u0 u1 curv2d . . .*

Body statement for free-form geometry.
Specifies a sequence of curves to build a single outer trimming loop.

u0 is the starting parameter value for the trimming curve *curv2d*.

u1 is the ending parameter value for the trimming curve *curv2d*.

curv2d is the index of the trimming curve lying in the parameter space of the surface. This curve must have been previously defined with the *curv2* statement.

hole *u0 u1 curv2d* *u0 u1 curv2d . . .*

Body statement for free-form geometry.
Specifies a sequence of curves to build a single inner trimming loop (hole).

u0 is the starting parameter value for the trimming curve *curv2d*.

u1 is the ending parameter value for the trimming curve *curv2d*.

curv2d is the index of the trimming curve lying in the parameter space of the surface. This curve must have been previously defined with the *curv2* statement.

scrv *u0 u1 curv2d* *u0 u1 curv2d . . .*

Body statement for free-form geometry.
Specifies a sequence of curves which lie on the given surface to build a single special curve.

u0 is the starting parameter value for the special curve *curv2d*.

u1 is the ending parameter value for the special curve *curv2d*.

curv2d is the index of the special curve lying in the parameter space of the surface. This curve must have been previously defined with the *curv2* statement.

sp *vp1* *vp. . .*

Body statement for free-form geometry.
Specifies special geometric points to be associated with a curve or surface. For space curves and trimming curves, the parameter vertices must be 1D. For surfaces, the parameter vertices must be 2D.

vp is the reference number for the parameter vertex of a special point to be associated with the parameter space point of the curve or surface.

end

Body statement for free-form geometry.
Specifies the end of a curve or surface body begun by a *curv*, *curv2*, or *surf* statement.

Examples

1. Taylor curve

For creating a single-segment Taylor polynomial curve of the form:

$$x = 3 + 2.3t + 7.98t^2 + 8.3t^3 + 6.34t^4$$
$$y = 1 - 10.1t + 5.4t^2 - 4.7t^3 + 2.03t^4$$
$$z = -2.5 + 0.5t - 7.0t^2 + 18.1t^3 + 0.08t^4$$

and evaluated between the global parameters 0.5 and 1.6:

```
v   3.000    1.000   -2.500
v   2.300  -10.100    0.500
v   7.980    5.400   -7.000
v   8.300   -4.700   18.100
v   6.340    2.030    0.080
cstype taylor
deg 4
curv 0.500 1.600 1 2 3 4 5
parm u 0.000 2.000
end
```

2. Bezier curve

This example shows a non-rational Bezier curve with 13 control points.

```
v -2.300000 1.950000 0.000000
v -2.200000 0.790000 0.000000
v -2.340000 -1.510000 0.000000
v -1.530000 -1.490000 0.000000
v -0.720000 -1.470000 0.000000
v -0.780000 0.230000 0.000000
v 0.070000 0.250000 0.000000
v 0.920000 0.270000 0.000000
v 0.800000 -1.610000 0.000000
v 1.620000 -1.590000 0.000000
v 2.440000 -1.570000 0.000000
v 2.690000 0.670000 0.000000
v 2.900000 1.980000 0.000000
# 13 vertices

cstype bezier
ctech cparm 1.000000
deg 3
curv 0.000000 4.000000 1 2 3 4 5 6 7 8 9 10 \
11 12 13
parm u 0.000000 1.000000 2.000000 3.000000  \
4.000000
end
# 1 element
```

3. B-spline surface

This is an example of a cubic B-spline surface.

```
g bspatch
v -5.000000 -5.000000 -7.808327
v -5.000000 -1.666667 -7.808327
v -5.000000 1.666667 -7.808327
v -5.000000 5.000000 -7.808327
v -1.666667 -5.000000 -7.808327
v -1.666667 -1.666667 11.977780
v -1.666667 1.666667 11.977780
v -1.666667 5.000000 -7.808327
v 1.666667 -5.000000 -7.808327
v 1.666667 -1.666667 11.977780
v 1.666667 1.666667 11.977780
v 1.666667 5.000000 -7.808327
v 5.000000 -5.000000 -7.808327
v 5.000000 -1.666667 -7.808327
v 5.000000 1.666667 -7.808327
v 5.000000 5.000000 -7.808327
# 16 vertices

cstype bspline
stech curv 0.5 10.000000
deg 3 3
8surf 0.000000 1.000000 0.000000 1.000000 13 14 \
15 16 9 10 11 12 5 6 7 8 1 2 3 4
parm u -3.000000 -2.000000 -1.000000 0.000000  \
1.000000 2.000000 3.000000 4.000000
parm v -3.000000 -2.000000 -1.000000 0.000000  \
1.000000 2.000000 3.000000 4.000000
end
# 1 element
```